
XTS TRANSPORT LAYER – Station Class



XTS TRANSPORT LAYER – Station Class



- Station based approach
 - fb_StationBase
 - Abstract class
 - Offers uniform station handling
 - Use of REFERENCE pointers
 - Datafields are set via accompanied properties
 - Such properties do not have a Get accessor, since access outside this class shall be done on the original datafield.



- Station based approach
 - fb_StationBase
 - Abstract class
 - Offers uniform station handling
 - Use of REFERENCE pointers
 - Datafields are set via accompanied properties
 - Such properties do not have a Get accessor, since access outside this class shall be done on the original datafield.


```
// XTS Stations
FOR nStation := 1 TO MAX STATION
DO
 IF (GVL_XTS.StationParameter[nStation].eType = E_STATION_TYPE.STATION_PROCESS)
 THEN
   GVL XTS.Station[nStation].StationId := nStation;
   GVL_XTS.Station[nStation].MessageLevel:= GVL_MSG.MessageLevelStations[nStation];
    GVL XTS.StationListItf[nStation]
                                          := GVL XTS.StationList[nStation];
    GVL XTS.StationCtrlItf[nStation]
                                          := GVL XTS.Station[nStation];
    GVL_XTS.Station[nStation].Ctrl
                                          REF= GVL_XTS.StationCtrl;
                                          REF= GVL XTS.StationState;
    GVL XTS.Station[nStation].ItfStations REF= GVL XTS.StationListItf;
    GVL_XTS.Station[nStation].ItfMover
                                          REF= GVL XTS.MoverItf;
                                          REF= GVL XTS.AxisRefMover;
   GVL XTS.Station[nStation].Mover
    GVL_XTS.Station[nStation].MoverOffset REF= GVL_XTS.PositionOffset;
    GVL_XTS.Station[nStation].StationParameter REF= GVL_XTS.StationParameter;
   GVL XTS.Station[nStation].Cycle();
    GVL_XTS.StationQueue[nStation]
                                          := GVL XTS.StationListItf[nStation].Data;
```

- Station based approach
 - fb_StationBase
 - Abstract class
 - Offers uniform station handling
 - Use of REFERENCE pointers
 - Datafields are set via accompanied properties
 - Such properties do not have a Get accessor, since access outside this class shall be done on the original datafield.

```
stCtrl
                           : REFERENCE TO ARRAY[1..MAX_STATION] OF ST_STATION_CTRL;
_stState
                           : REFERENCE TO ARRAY[1..MAX_STATION] OF ST_STATION_STATE;
_eCmd,
eCmdOld
                           : E STATION CTRL;
ItfStation
                           : REFERENCE TO ARRAY[1..MAX STATION] OF I Station LinkedList;
_ItfMover
                           : REFERENCE TO ARRAY[1..MAX_MOVER]
                                                                 OF I_XtsTransport_Mover;
// station related data
rMoverOffset
                           : REFERENCE TO ARRAY[1..MAX_STATION] OF T_NEST_OFFSET;
                           : REFERENCE TO ARRAY[1..MAX_STATION] OF ST_STATION_PARAMETER;
stParameter
                           : REFERENCE TO ARRAY[1..MAX_MOVER]
                                                                 OF AXIS REF;
Mover
```



- Station based approach
 - fb_Station_LinkedListCtrl
 - Linked List
 - Transport of information
 - My ticket.
 - ST_STATION_MOVER_DATA.nMoverId
 - My destination.
 - ST_STATION_MOVER_DATA. nTargetStation
 - My compartement(s).
 - ST_STATION_MOVER_DATA.nMask
 - My seat.
 - ST_STATION_MOVER_DATA.rOffset



- Station based approach
 - fb_Station_LinkedListCtrl
 - Tc2_Utilities.FB_LinkedListCtrl
 - Atomic access
 - Global Instances
 - Station Queues for diag and visu
 - Used via Interface

```
I_Station_LinkedList

AddHeadValue

AddTailValue

Count

Data

Free

GetHead


InitList

RemoveHeadValue
```

```
// station handshaking with mover and extern process
// station sends mover to target station/WaitPos
// station adds mover data to LinkedList.AddTail() of target station
Station
                    : ARRAY[1..MAX_STATION] OF fb_StationProcess;
StationList
                    : ARRAY[1..MAX STATION] OF fb Station LinkedListCtrl;
StationQueue
                    : ARRAY[1..MAX STATION]
                      ARRAY[1..MAX LIST NODES] OF ST STATION MOVER DATA;
// interface for access to List methods
StationListItf
                   : ARRAY[1..MAX STATION] OF I Station LinkedList;
// interface for access to station methods
StationCtrlItf
                    : ARRAY[1..MAX_STATION] OF I_XtsTransport_Station;
```

- Station based approach
 - fb_StationProcess / fb_StationGearInPos
 - Extend fb_StationBase
 - Global array of indexed Stations (nStationId)
 - Cycle()
 - State Machine for handshaking movements of mover in station
 - Ctrl/State pair
 - Mover is detected by:
 - _ltfStation[nStationId].Count > 0
 - Mover ID is copied from ticket
 - − → LinkedList must be correct!
 - → Movement is used for inherently sorted list.

- Station based approach
 - fb_StationProcess / fb_StationGearInPos
 - Use of LinkedList at station infeed:
 - Get top entry of list (Head)
 - Plausibility checks of ticket data
 - Station switched to STATION_MOVER_ENTER
 - You decide what to do next.
 - Disable:
 - E_STATION_CTRL.STATION_DISABLE
 - Infeed to position / GearIn to MasterAxis:
 - E_STATION_CTRL.STATION_MOVER_ENTER
 - Send mover to new target:
 - E_STATION_CTRL.STATION_MOVER_SEND



- Station based approach
 - fb_StationProcess E_STATION_CTRL.STATION_MOVER_ENTER:
 - E_PROGRESS_INIT:
 - Checks after seeing the command to let mover into station:
 - Get first active nest position in _stMoverData.nMask (1 = default)
 - If nMask == 0 → only one Stop, then mover has to leave
 - For 1 stop stations you need not to use nMask
 - E_PROGRESS_BUSY:
 - MoveIn(): prepares movement to PosStop with all offsets included
 - Check whether mover has to cross modulo turn

- Station based approach
 - fb_StationGearInPos E_STATION_CTRL.STATION_MOVER_ENTER:
 - E_PROGRESS_INIT:
 - Same as before
 - E_PROGRESS_BUSY:
 - Check for minimal distance to sync position (warning set if not)
 - E_PROGRESS_PREPARE:
 - MoveIn(): prepares movement to SlaveSyncPos with all offsets included
 - Check whether mover has to cross modulo turn

- Station based approach
 - fb_StationProcess E_STATION_STATE.STATION_MOVER_IN_TARGET:
 - Start movement:
 - MoveToPosCA movement with InTarget and NotMoving check.
 - Result (E_PROGRESS)
 - Checks for DONE or ERROR and sets state machine accordingly


- → E_STATION_STATE.STATION_PROCESS_START
 - Handshake state(s) for your process flow
 - See flowcharts for details (Example pdfs)

- Station based approach
 - fb_StationGearInPos E_STATION_STATE.STATION_MOVER_IN_TARGET:
 - Start GearInPos:
 - GearInPosCA GearIn to MasterAxis at SlaveSyncPosition.
 - Result (E_PROGRESS)
 - Checks for DONE or ERROR and sets state machine accordingly
 - PROGRESS_DONE:
 - StartPosition of sync movement is latched
 - Mover is now nSync with the master AND is still moving
 - → E_STATION_STATE.STATION_PROCESS_START
 - Handshake state(s) for your process flow
 - Three options available
 - MOVER_OUT: fast release without checking SyncDistance
 - PROCESS_START: , PROCESS_DONE)

- Station based approach
 - fb_StationGearInPos E_STATION_STATE.STATION_PROCESS_START:
 - Mover IS moving nSync with MasterAxis:
 - According to _stParameterGear.eDistance: Synchrone Distance(DiffPosition) calculation starts
 - Handshake state(s) for your process flow
 - Options available for Ctrl:
 - MOVER_OUT: fast release without checking SyncDistance
 - PROCESS_START, PROCESS_DONE:
 - state change to STATION_PROCESS_DONE.

- Station based approach
 - fb_StationGearInPos E_STATION_STATE.STATION_PROCESS_DONE:
 - Mover IS still moving nSync with MasterAxis:
 - According to _stParameterGear.eDistance: Synchrone Distance(DiffPosition) calculation continues
 - Handshake state(s) for your process flow
 - Three handshake options available for Ctrl:
 - MOVER_OUT: fast release without checking SyncDistance
 - PROCESS_START: requires second handshake
 - PROCESS_DONE: changes to MOVER_OUT after having moved SyncDistance

- Station based approach
 - fb_StationProcess / fb_StationGearInPos
 - Use of LinkedList at station outfeed:
 - Get ticket data from Ctrl
 - Plausibility checks of ticket data
 - Wait for command from Ctrl
 - Delete top entry of LinkedList
 - Wait until mover has moved specified distance
 - ST_STATION_PARAMETER.rReleaseDistance
 - Add bottom (Tail) entry in LinkedList of ST_STATION_CTRL.nTargetStation.




- Station based approach: ST_STATION_PARAMETER
 - Configuration parameters
 - Station Type
 - Absolute modulo positions as target
 - Waiting Position
 - Relative stop positions
 - Additional quantification of possible stop positions
 - Dynamic constraint of mover in station
 - Relative distance to leave station


```
ST_STATION_PARAMETER → X GVL_XTS
        TYPE ST_STATION_PARAMETER :
\Box
        STRUCT
          eType
                            : E STATION TYPE := 1; // StationProcess or StationGearInPos
                            : STRING(80);
                                                     // only description
          sText
          rPosWait
                            : REAL;
                                                     // start of station,
                                                     // a sending station is using this value
                                                     // to send mover to
          rReleaseDistance : REAL;
                                                     // distance mover has to travel (from ActPos)
                                                     // in order for station to go back to disable
                            : REAL;
          rGap
          rVelo
                            : REAL;
          rAccDec
                            : REAL;
          rJerk
                            : REAL;
\Box
         // how many nests (stop positions) mover has to stop at (1 = default)
          nConfiguredStopCount : USINT := 1; // 1-8 --> NestMask = BYTE
         // mover stop position in station, relative to rPosWait!!
          rPosStop
                            : ARRAY[1..8] OF LREAL;
        END_STRUCT
        END TYPE
```



- XTS_DEMO_11
 - Simple single stations
 - One stop only
 - Target is always next station




- XTS_DEMO_11
 - Simple handshakes
 - Ctrl/State pair



Use Cases BECKHOFF

Ex01

- XTS_DEMO_11
 - Station configuration
 - WaitPos (absolute modulo)
 - ConfiguredStopCount := 1
 - StopPos[1] (relative)
 - ReleaseDistance > 0



Use Cases

- XTS_DEMO_APPLICATION_108
 - Application requires grouping of stations
 - Process definition:
 - One handshake that may be performed on one or many fb_StationProcess simultaneously
 - Use of global stations Ctrl/State pairs


- Stations must be mutable
 - Is done before enabling of stations

- Stations work parallel
 - One Ctrl/State pair for process

- Range of stations must be defined
 - Close range
 - LastStation (index in global array)
 - FirstStation (index in global array)




- Application requires product transport without gaps.
 - Infeed Buffer [1]: controls one station
 - Target Infeed [1 to 12] as specified
 - may contain gaps → no mover must be sent to gap.
 - Infeed [1 to12]: controls 12 stations
 - One stop only
 - Target Outfeed Buffer [1]





Use Cases

- See placement example pdfs in doc folder!
- Station parameters are hard coded in MAIN actions
- Process parameters are hard coded in MAIN_APP actions



Use Cases BECKHOFF

- fb_ProcessCollector
 - Class for grouping stations
 Ctrl/State pairs
 - Writes commands to stations

```
FUNCTION_BLOCK fb ProcessCollector EXTENDS fb StationCollector IMPLEMENTS I ProcessCollector
VAR
  nProcessId
                 : E INSTANCE; // whoami
  stControl
                 : REFERENCE TO ST PROCESS CTRL; // ctrl via property
  stState
                 : REFERENCE TO ST PROCESS STATE; // state via property
  eCmd,
  eCmdOld
                 : E_PROCESS_CTRL; // logging of command on change
                                     // progress sub state for process
  _eStateProgress : E_PROGRESS;
                                    // progress result for methods
  eResult
                 : E PROGRESS;
  // ctrl words for XtsStations
  {attribute 'displaymode':='bin'}
  wActivateStation : T PROCESS; // bits enable XtsStations in this process
  // ctrl data for used target XtsStations in target process
  {attribute 'displaymode':='bin'}
  _wTargetMask
                       : ARRAY[1..SIZEOF(T_PROCESS)*8] OF BYTE;
                                                                  // mask for multiple PosStop in target
  _rTargetOffset
                       : ARRAY[1..SIZEOF(T_PROCESS)*8] OF LREAL; // dyn offset for mulriple PosStop in target
  nTargetIndex
                       : ARRAY[1..SIZEOF(T PROCESS)*8] OF USINT; // index of XtsStation in target process
```

```
Collector
  △ 🚉 E PROCESS CTRL (ENUM)
  △ 🚉 E PROCESS STATE (ENUM)
 ▲ a fb ProcessCollector (FB)
   properties
    ActivateStation
    MessageLevel
    MoverCountTotal
    MoverPerMinute
    ▶ ■ ProcessCtrl
    ▶ ₱ ProcessId
    ProcessState
    TargetIndex
    TargetMask
    R Controls
    🙀 Cycle
    Init
    👪 LogControl
     Template
```

Use Cases BECKHOFF

- XTS_DEMO_APPLICATION_108
 - fb_StationCollector
 - Collects station states in bitmasks

```
▲ a fb_StationCollector (FB)
  properties
   ▶ B MoverInfo
   QueueMoverIDs
   QueueProcessCount
   QueueStationCount
   StationCount
   ▶ ■ StationCtrl
   ▶ 母 StationFirst
   ▶ ■ StationLast
   StationState
   BitsToString
   R Check


    □ DelBit

☐ GetBit

   GetMoverInStation
   GetStationState
   R SetBit
   M States
    To_T_Process
```




- Process Ctrl/State pairs
 - Single command structure for grouped stations
 - See handshake
 fb_ProcessCollector_Cycle.pdf
 in doc folder of project



Use Cases

- Process Ctrl/State pairs
 - Single command structure for grouped stations
 - See handshake
 fb_ProcessCollector_Cycle.pdf
 in doc folder of project



LICENSE

XTS_TRANSPORT_LAYER project

MIT License Copyright (c) 2025 HAUD

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS ORIMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THEAUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHERLIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THESOFTWARE.